



- Open Eunhasu Web GUI
- Run Squeezelite mode and start Squeezelite mode and open LMS.




- Click Settings button
 - If the ickStream app was installed, you can see the app in Home → My Apps.
 - Click Settings button at the right bottom side.




- Install ickStream App
 - Go to Plugins tabs, and scroll down to the bottom page.
 - Enter the url below in the blank box at the bottom side of the page and click Apply button.
 - SMS-200: <http://repository.ickstream.com/squeezebox/repository-linuxarmhf.xml>
 - SMS-1000: <http://repository.ickstream.com/squeezebox/repository-linux.xml>
 - Once the new windows appear, click OK to install ickStream App.
 - Enable 'ickStream' at Updated plugins available section, and click Apply button.




- Click 'Reboot Now' and open LMS again.



- Click Settings button
 - A. If the ickStream app was installed, you can see the app in Home → My Apps.
 - B. Click Settings button at the right bottom side.



- Check ickStream app.
 - You can see ickStream app in My Apps.
 - Check Settings → Advanced tab , the ickStream setting menu will be appeared as the image below.



From: <https://www.docs.sotm-audio.com/> - **SOTM docs**

Permanent link: https://www.docs.sotm-audio.com/doku.php?id=en:how_to_install_ickstream_app_in_lms&rev=1479355016

Last update: **2016/11/16 22:56**

